


# Installation of Aspen

1. Connect to OSU VPN  
(required to communicate with Aspen server in step 13)
  - Vpn website: <https://it.okstate.edu/services/osuvpn/index.html>
2. Unzip compressed folder
3. Right click on the compressed folder and select “Extract All”
4. Click the Extract button
5. Open the un-zipped folder
6. Run the setup file



7. Under the Please select the software below to begin Install
  - a. Select “aspENONE Engineering V10”

Welcome to aspenONE V10.1 Installer



Browse contents of USB

PLEASE SELECT THE SOFTWARE BELOW TO BEGIN INSTALL

**> aspenONE Engineering V10**  
aspenONE Software License Manager V10

INSTALLATION DETAILS

aspenONE® Engineering is a suite of industry leading, highly integrated products for optimized design and operations of process manufacturing plants. The suite includes products such as Aspen HYSYS, Aspen Plus, Aspen Capital Cost Estimator, Aspen Exchanger Design & Rating, and more.

**Begin Install**

Use Custom Install



**Need Help?**  
Visit the AspenTech Support Center  
[Learn More>](#)


**Getting Started**  
Learn about how to install our software, the platform requirements and other helpful information to get started.  
[Learn More>](#)

**What's New In V10.1**  
Discover what's new in our Asset Optimization Software: Engineering, Manufacturing & Supply Chain and Asset Performance Management.  
[View Details>](#)

8. Click the blue “Begin Install” button
9. Click “Install aspenONE products”

aspensONE Installer

## Welcome to the aspenONE Engineering V10 Installer



The aspenONE Installer will guide you through the necessary steps to install or upgrade products, configure licensing, and create install script for unattended installation. aspenONE V10 Products requires SLM License Server from V10 or higher. Before you install any aspenONE products, we recommend that you install and configure the SLM License Server software on the computer you have chosen to be your license server.

AspenTech provides software in both 32-bit and 64-bit versions, which can now be installed from a single workflow.


-  **Install aspenONE products**  
Install aspenONE Engineering V10.
-  **Upgrade or repair existing products**  
Upgrade earlier versions of products or repair existing installation errors. Existing products and features will be reinstalled to fix missing and corrupt files.

**Administrative Workflow:**

-  **Prepare Deployments (For IT Personnel/Deployment Groups)**  
Configure recording options for Silent Install script and copy media to automate software deployment.
-  **Install and configure SLM (Software License Manager) software**  
Install and configure the SLM Server running on a network. The SLM Server is required for network licenses.


Get Started  
Installation Guides  
Release Notes  
aspensONE Product Documentation  
aspensONE Update Center  
Unattended Install Notes  
Support Services  
AspenTech Home  
Contact Us

10. Click the checkbox to agree to the terms of the license agreement and then click Next




11. Click Next again


12. Copy and paste "aspen.ceatlabs.okstate.edu" into the license server box



13. Click the “Add Server” button



14. Click Next




15. Click the “Install Now” button

16. Once everything has finished installing, click the “Finish” button

aspenONE Installer

### aspenONE installation progress



Overall installation progress:

100%


Component	Progress	Status
aspenONE Product	100%	Complete. Reboot requested
Process Modeling (Aspen ...)	100%	Complete
Process Modeling (Aspen ...)	100%	Complete
Aspen Exchanger Design ...	100%	Complete
Aspen Economic Evaluation	100%	Complete

The installation has completed.

[View Log File](#)

[Finish](#)

17. Click the "Reboot Now" button




18. Aspen should open after the computer and will prompt to install updates

19. Click "Next"

aspenONE Update Agent

## Welcome to aspenONE Update Agent



► **Welcome**

- View Installed Products
- Install Updates...
- Install Summary

Update Agent lets you review the AspenTech software installed on this machine and apply the available/applicable software updates.

Click Next to install the patches.

Copyright © 2017, Aspen Technology, Inc. All rights reserved.


< Back   Next >   Close

20. Under the View Installed Products page click “Next” again

21. Verify that all patches are checked and click “Install”

aspenONE Update Agent

## aspenONE product updates



- Welcome
- View Installed Products
- **Install Updates...**
- Install Summary


<input checked="" type="checkbox"/>	Patch Name	Patch Status	aspenONE Version
<input checked="" type="checkbox"/>	Aspen OnLine V10 CP1	Update available 	V10
<input checked="" type="checkbox"/>	Aspen Simulation Workbook V10 CP1	Update available 	V10

Ready to install...

< Back   Install   Close

Copyright © 2017, Aspen Technology, Inc. All rights reserved.

22. Once the updates are installed click "Next"



The screenshot shows the AspenONE Update Agent window. The title bar reads "aspenONE Update Agent". The main header area features the text "aspenONE product updates" and the AspenTech logo. On the left, a navigation pane includes "Welcome", "View Installed Products", "Install Updates..." (highlighted with a blue arrow), and "Install Summary". The main content area displays a table of installed updates:


<input checked="" type="checkbox"/>	Patch Name	Patch Status	aspenONE Version
<input checked="" type="checkbox"/>	Aspen OnLine V10 CP1	Update Installed OK 	V10
<input checked="" type="checkbox"/>	Aspen Simulation Workbook V10 CP1	Update Installed OK 	V10

At the bottom of the window, there is a status bar with the text "Updates installed." and three buttons: "< Back", "Next >", and "Close". The copyright notice at the bottom left reads: "Copyright © 2017, Aspen Technology, Inc. All rights reserved."

23. Under the Install Summary page, click Finish

aspenONE Update Agent

## Installed aspenONE updates



Welcome

View Installed Products

Install Updates...

**► Install Summary**


Product Name	Patch Name	Version Found	Upgrade
Aspen OnLine V10	Aspen OnLine V10 CP1	36.0.0	36.0.1
Aspen Simulation Workbook V10	Aspen Simulation Workbook V10 CP1	36.0.0	36.0.1

Copyright © 2017, Aspen Technology, Inc. All rights reserved.

< Back
Next >
Finish

24. Click the “Reboot Now” button

25. After the computer restarts open any Aspen software




The image shows a Windows Start menu search for "Aspen Plus V10". The search results are categorized into "Best match", "Apps", "Search the web", and "Folders".


- Best match:** Aspen Plus V10 (App)
- Apps:**
  - Customize Aspen Plus V10
  - Set Version - Aspen Plus V10
  - Process Modeling (Aspen Plus) V10.msi - in Process Modeling (Aspen)
- Search the web:**
  - aspen Plus V10 - See web results
  - aspen plus v10 cp3
  - aspen plus v10 tank
- Folders:**
  - Aspen Plus V10.0
  - Process Modeling (Aspen Plus) V10 - in aspenoneengdvd
  - Process Modeling (Aspen Plus) V10 - in aspenoneengdvd

The right-hand pane shows the context menu for the "Aspen Plus V10" app, with the "Open" option selected. Other options include "Run as administrator", "Open file location", "Pin to Start", "Pin to taskbar", and "Uninstall".

26. A screen will pop-up prompting to Register Product. This window will pop-up every time you open an Aspen application
27. Close this window



28. A small window will open up showing progress



29. Once this window disappears the Aspen application should open

